

# QUADRILATERAL EDITOR trên CASIO fx-580VN X

## DATA (E9E0):

34 7B 31 30 31 F0 15 00 D2 03 32 30 34 7B 31 30  
86 08 86 38 64 8E 30 30 34 7B 31 30 36 08 36 38  
64 8E 30 30 34 7B 31 30 36 38 86 38 64 8E 30 30  
34 7B 31 30 36 08 86 08 64 8E 30 30 34 7B 31 30  
08 01 FC D9 CC 3D 32 30 34 7B 31 30 30 38 0D DA  
41 0C 32 30 34 7B 31 30 2F 02 0F DA 41 0C 32 30  
  
34 7B 31 30 87 02 11 DA 41 0C 32 30 34 7B 31 30  
87 38 13 DA 41 0C 32 30 7E 94 30 30 02 26 31 30  
CA D7 EA F5 32 30 30 07 32 30 CE D9 CE D9 A8 9F  
30 30 A6 7C 31 30 02 26 31 30 00 00 21 9C 30 30  
4A C6 31 30 74 1F 32 30 34 7B 31 30 44 EB FF FF  
D8 39 31 30 34 7B 31 30 58 EB FF FF D8 39 31 30  
  
34 7B 31 30 6C EB FF FF D8 39 31 30 78 5C 31 30  
8E D8 60 0D 32 30 34 7B 31 30 44 EB 01 00 D8 39  
31 30 34 7B 31 30 58 EB 01 00 D8 39 31 30 34 7B  
31 30 6C EB 01 00 D8 39 31 30 78 5C 31 30 8E D8  
60 0D 32 30 34 7B 31 30 44 EB 00 FF D8 39 31 30  
34 7B 31 30 58 EB 00 FF D8 39 31 30 34 7B 31 30  
  
6C EB 00 FF D8 39 31 30 78 5C 31 30 8E D8 60 0D

32 30 34 7B 31 30 44 EB 00 01 D8 39 31 30 34 7B  
31 30 58 EB 00 01 D8 39 31 30 34 7B 31 30 6C EB  
00 01 D8 39 31 30 78 5C 31 30 8E D8 60 0D 32 30  
74 89 31 30 00 00 A6 A8 30 30 FE E9 A0 9C 30 30  
30 30 30 30 74 89 31 30 00 00 A6 A8 30 30 09 EA  
  
A0 9C 30 30 30 30 30 30 74 89 31 30 00 00 A6 A8  
30 30 2C EA A0 9C 30 30 30 30 30 30 60 8C 30 30  
78 5C 31 30 C0 D9 60 0D 32 30 34 7B 31 30 4A EB  
FE E9 D8 39 31 30 34 7B 31 30 5E EB 09 EA D8 39  
31 30 34 7B 31 30 72 EB 2C EA D8 39 31 30 34 7B  
31 30 BB EC 41 00 D2 03 32 30 78 5C 31 30 C0 D9  
60 0D 32 30 34 7B 31 30 4A EB 14 EA D8 39 31 30  
  
34 7B 31 30 5E EB FC E9 D8 39 31 30 34 7B 31 30  
72 EB 38 EA D8 39 31 30 34 7B 31 30 BB EC 42 00  
D2 03 32 30 78 5C 31 30 C0 D9 60 0D 32 30 34 7B  
31 30 4A EB F0 E9 D8 39 31 30 34 7B 31 30 5E EB  
16 EA D8 39 31 30 34 7B 31 30 72 EB 44 EA D8 39  
31 30 34 7B 31 30 BB EC 43 00 D2 03 32 30 78 5C  
  
31 30 C0 D9 60 0D 32 30 34 7B 31 30 4A EB F2 E9  
D8 39 31 30 34 7B 31 30 5E EB 0A EA D8 39 31 30  
34 7B 31 30 72 EB 50 EA D8 39 31 30 34 7B 31 30  
BB EC 44 00 D2 03 32 30 78 5C 31 30 C0 D9 60 0D  
32 30 34 7B 31 30 30 D6 84 D1 CC 03 32 30 78 5C

31 30 2E D6 60 0D 32 30 01 01 D8 D8 01 02 12 D9

01 04 4C D9 02 01 86 D9 40 04 D6 D7 80 08 04 D8  
40 08 60 D8 80 04 32 D8 00 00 C0 D9 45 64 69 74  
69 6E 67 20 43 6F 72 6E 65 72 3A 41 00 41 00 42  
00 43 00 44 00 00 00 00 00 00 00 00 00 00 00 00  
00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00  
00 00 00 00 00 00 00 00 00 00 00 00 00 00 00 00

**LAUNCHER (D180):**

FD 24 30 30 DA 7B 31 30 FE 02 E0 E9 30 D7 2E D7  
32 89 31 30 30 30 74 1F 32 48

• **Token:**

@ 0 0 r cos<sup>-1</sup>( 10 cm in G Simp 0 % . % 2 LcM( 1 0 0 0  
v( @ 2 x

• **Assign Hex:**

@ = 1. 00 00 FD 24 E9 1F 23

**KEY BINDINGS:**

[◀] [▶] [▼] [▲]: Điều khiển  
[1] [2] [3] [4]: chọn góc

**NOTE:**

- Không để hình tứ giác chạy khỏi màn hình khi điều khiển.

**CREATERS:**

Original - Dev by @kator  
Cre - Dev by WHACK STUDIO

28/12/2025